

The pdfcolparcolumns package

Heiko Oberdiek*

2019/12/29 v1.5

Abstract

Since version 1.40 pdfTeX supports several color stacks. This package uses them to fix color problems in package `parcolumns`.

Contents

| | |
|--|----------|
| 1 Usage | 2 |
| 1.1 Option <code>rulebetweencolor</code> | 2 |
| 1.2 Future | 2 |
| 2 Implementation | 2 |
| 2.1 Identification | 2 |
| 2.2 Load packages | 2 |
| 2.2.1 Package <code>parcolumns</code> | 2 |
| 2.2.2 Package <code>pdfcol</code> | 3 |
| 2.2.3 Package <code>infwarerr</code> | 3 |
| 2.3 Color stack macros | 3 |
| 2.4 Patches | 3 |
| 2.4.1 Init stacks | 3 |
| 2.4.2 Switch stack | 3 |
| 2.4.3 Set current stack color | 4 |
| 3 Installation | 6 |
| 3.1 Download | 6 |
| 3.2 Bundle installation | 6 |
| 3.3 Package installation | 6 |
| 3.4 Refresh file name databases | 6 |
| 3.5 Some details for the interested | 7 |
| 4 References | 7 |
| 5 History | 7 |
| [2007/07/26 v1.0] | 7 |
| [2007/09/09 v1.1] | 7 |
| [2008/08/11 v1.2] | 7 |
| [2010/01/11 v1.3] | 8 |
| [2016/05/16 v1.4] | 8 |
| [2019/12/29 v1.5] | 8 |
| 6 Index | 8 |

*Please report any issues at <https://github.com/ho-tex/oberdiek/issues>

1 Usage

```
\usepackage{pdfcolparcolumns}
```

The package `pdfcolparcolumns` loads package `parcolumns` [1]. If color stacks are available then the macros of `parcolumns` are patched to add support for color stacks.

1.1 Option `rulebetweencolor`

Package `pdfcolparcolumns` also fixes the color for the rule between columns (if `rulebetween` is set). Default color is `\normalcolor`. But this can be changed by using option `rulebetweencolor`. It takes a color specification as value. If the value is empty, then the default (`\normalcolor`) is used. Examples:

```
rulebetweencolor=blue,  
rulebetweencolor={red},  
rulebetweencolor={}, % \normalcolor is used  
rulebetweencolor=[rgb]{1,0,.5} % see below
```

If used inside the optional argument of environment `parcolumns` and the value contains an optional argument, then whole value must be put in curly braces:

```
\begin{parcolumns}[  
  rulebetween,  
  rulebetweencolor={ [rgb]{1,0,.5} },  
]{2}  
  ...  
\end{parcolumns}
```

This option `rulebetweencolor` can also be set using `\setkeys`:

```
\setkeys{parcolumns}{rulebetweencolor=green}
```

1.2 Future

Currently package `parcolumns` does not seem to be maintained. Nevertheless if there will be a new version that adds support for color stacks, then this package may become obsolete.

2 Implementation

2.1 Identification

```
1 (*package)  
2 \NeedsTeXFormat{LaTeX2e}  
3 \ProvidesPackage{pdfcolparcolumns}%  
4 [2019/12/29 v1.5 Color stacks for parcolumns (HO)]%
```

2.2 Load packages

2.2.1 Package `parcolumns`

Currently package `parcolumns` does not define options. Thus it is just a precaution that the options of package `pdfcolparcolumns` are passed to package `parcolumns`.

```
5 \DeclareOption*{%  
6   \PassOptionsToPackage{\CurrentOption}{parcolumns}%  
7 }  
8 \ProcessOptions\relax  
9 \RequirePackage{parcolumns}[2004/11/25]
```

2.2.2 Package pdfcol

```
10 \RequirePackage{pdfcol}[2007/09/09]
11 \ifpdfcolAvailable
12 \else
13   \PackageInfo{pdfcolparcolumns}{%
14     Loading aborted, because color stacks are not available%
15   }%
16   \expandafter\endinput
17 \fi
```

2.2.3 Package infwarerr

```
18 \RequirePackage{infwarerr}[2007/09/09]
```

2.3 Color stack macros

`\pcpc@MaxStack` Macro `\pcpc@MaxStack` holds the highest number of allocated stacks.

```
19 \global\chardef\pcpc@MaxStack=\z@
```

`\pcpc@InitStacks` Macro `\pcpc@InitStacks` takes the number of columns as argument and ensures that there are enough color stacks for all columns.

```
20 \def\pcpc@InitStacks#1{%
21   \ifnum#1>\pcpc@MaxStack
22     \begingroup
23       \count@\pcpc@MaxStack
24       \loop
25         \advance\count@\@ne
26         \pdfcolInitStack{pcpc@\the\count@}%
27       \ifnum#1>\count@
28         \repeat
29       \global\chardef\pcpc@MaxStack=\count@
30     \endgroup
31   \fi
32 }
```

`\pcpc@SwitchStack`

```
33 \def\pcpc@SwitchStack#1{%
34   \pdfcolSwitchStack{pcpc@\number#1}%
35 }
```

`\pcpc@SetCurrent`

```
36 \def\pcpc@SetCurrent#1{%
37   \pdfcolSetCurrent{pcpc@\number#1}%
38 }
```

2.4 Patches

Now the color stack macros are patched into the macros of package `parcolumns`.

2.4.1 Init stacks

`\pcpc@InitStacks` should go into the definition of environment `parcolumns`. `\pc@alloccolumns` is executed there and nowhere else, thus we hook into it.

```
39 \g@addto@macro\pc@alloccolumns{%
40   \pcpc@InitStacks\pc@columncount
41 }
```

2.4.2 Switch stack

`\pcpc@SwitchStack` should be called by macro `\colchunk@`. However it is easier to patch `\pc@setcolumnwidth` that is executed in `\colchunk@` only.

```
42 \g@addto@macro\pc@setcolumnwidth{%
```

```
43 \pcpc@SwitchStack\pc@columnctr
44 }
```

2.4.3 Set current stack color

\pcpc@SetCurrent is set at the begin of each line. It must be inserted into \pc@placeboxes. Unhappily there is no easy way. Therefore we check and redefine \pc@placeboxes.

```
45 \beginngroup
46 \def\x{%
47 \global\let\@tempa\relax
48 \count\z@
49 \hb@xt@\linewidth{%
50 \vfuzz30ex %
51 \vbadness\@M
52 \splittopskip\z@skip
53 \loop
54 \ifnum\count@<\pc@columncount
55 \advance\count@\@ne
56 \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
57 \hskip\csname pc@column@width@\number\count@\endcsname
58 \else
59 \expandafter\setbox\expandafter\@tempboxa\expandafter
60 \vsplit\csname pc@column@\number\count@\endcsname
61 to \dp\strutbox
62 \vbox{%
63 \unvbox\@tempboxa
64 }%
65 \fi
66 \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
67 \else
68 \global\let\@tempa\pc@placeboxes
69 \fi
70 \ifnum\count@<\pc@columncount
71 \strut
72 \hfill
73 \ifpc@rulebetween
74 \vrule
75 \hfill
76 \fi
77 \fi
78 \repeat
79 }%
80 \@tempa
81 }%
82 \ifx\x\pc@placeboxes
83 \else
84 \@PackageWarningNoLine{pdfcolparcolumns}{%
85 Command \string\pc@placeboxes\space has changed.\MessageBreak
86 Supported versions of package 'parcolumns':\MessageBreak
87 \space\space 2004/08/05.\MessageBreak
88 The redefinition of \string\pc@placeboxes\space may not%
89 \MessageBreak
90 behave correctly depending on the changes%
91 }%
92 \fi
93 \endgroup

\pc@placeboxes

94 \renewcommand*\pc@placeboxes{%
95 \global\let\@tempa\relax
96 \count\z@
```

```

97 \hb@xt@\linewidth{%
98 \vfuzz30ex %
99 \vbadness\@M
100 \splittopskip\z@skip
101 \loop
102 \ifnum\count@<\pc@columncount
103 \advance\count@\@ne
104 \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
105 \hskip\csname pc@column@width@\number\count@\endcsname
106 \else
107 \expandafter\setbox\expandafter\@tempboxa\expandafter
108 \vsplit\csname pc@column@\number\count@\endcsname
109 to \dp\strutbox
110 \vbox{%
111 \pcpc@SetCurrent\count@
112 \unvbox\@tempboxa
113 }%
114 \fi
115 \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
116 \else
117 \global\let\@tempa\pc@placeboxes
118 \fi
119 \ifnum\count@<\pc@columncount
120 \strut
121 \hfill
122 \ifpc@rulebetween
123 \begingroup
124 \pcpc@RuleBetweenColor
125 \vrule
126 \endgroup
127 \hfill
128 \fi
129 \fi
130 \repeat
131 }%
132 \@tempa
133 }

```

\pcpc@RuleBetweenColorDefault

```

134 \def\pcpc@RuleBetweenColorDefault{%
135 \normalcolor
136 }

```

\pcpc@RuleBetweenColor

```

137 \let\pcpc@RuleBetweenColor\pcpc@RuleBetweenColorDefault
138 \define@key{parcolumns}{rulebetweencolor}{%
139 \edef\pcpc@temp{#1}%
140 \ifx\pcpc@temp\@empty
141 \let\pcpc@RuleBetweenColor\pcpc@RuleBetweenColorDefault
142 \else
143 \edef\pcpc@temp{%
144 \noexpand\@ifnextchar [%
145 \def\noexpand\pcpc@RuleBetweenColor{%
146 \noexpand\color\pcpc@temp
147 }%
148 \noexpand\pcpc@GobbleNil
149 }{%
150 \def\noexpand\pcpc@RuleBetweenColor{%
151 \noexpand\color{\pcpc@temp}%
152 }%
153 \noexpand\pcpc@GobbleNil
154 }%

```

```

155     \pcpc@temp\noexpand\@nil
156   }%
157   \pcpc@temp
158   \fi
159 }

```

```
\pcpc@GobbleNil
```

```

160 \long\def\pcpc@GobbleNil#1\@nil{}
161 \end{package}

```

3 Installation

3.1 Download

Package. This package is available on CTAN¹:

[CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.dtx](#) The source file.

[CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.pdf](#) Documentation.

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/oberdiek.tds.zip](#)

TDS refers to the standard “A Directory Structure for T_EX Files” ([CTAN:pkg/tds](#)). Directories with `texmf` in their name are usually organized this way.

3.2 Bundle installation

Unpacking. Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

3.3 Package installation

Unpacking. The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain T_EX:

```
tex pdfcolparcolumns.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

```

pdfcolparcolumns.sty → tex/latex/oberdiek/pdfcolparcolumns.sty
pdfcolparcolumns.pdf → doc/latex/oberdiek/pdfcolparcolumns.pdf
pdfcolparcolumns.dtx → source/latex/oberdiek/pdfcolparcolumns.dtx

```

If you have a `docstrip.cfg` that configures and enables `docstrip`’s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

3.4 Refresh file name databases

If your T_EX distribution (T_EX Live, MiK_TE_X, ...) relies on file name databases, you must refresh these. For example, T_EX Live users run `texhash` or `mktexlsr`.

¹[CTAN:pkg/pdfcolparcolumns](#)

3.5 Some details for the interested

Unpacking with L^AT_EX. The `.dtx` chooses its action depending on the format:

plain T_EX: Run `docstrip` and extract the files.

L^AT_EX: Generate the documentation.

If you insist on using L^AT_EX for `docstrip` (really, `docstrip` does not need L^AT_EX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdfcolparcolumns.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfL^AT_EX:

```
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
```

4 References

- [1] Jonathan Sauer: *The parcolumns package*; 2004/11/25;
CTAN:pkg/parcolumns.
- [2] Heiko Oberdiek: *The pdfcol package*; 2007/09/09;
CTAN:pkg/pdfcol.

5 History

[2007/07/26 v1.0]

- First version, published in the newsgroup `comp.text.tex` with the name `parcolumns-colorstacks`: “Re: `xcolor` glitches”²

[2007/09/09 v1.1]

- CTAN version, package name renamed to `pdfcolparcolumns`.
- Uses package `pdfcol`.
- Documentation added.
- Test file added.

[2008/08/11 v1.2]

- Code is not changed.
- URLs updated.

²Url: <https://groups.google.com/group/comp.text.tex/msg/56bd897b11bca414>

[2010/01/11 v1.3]

- Fix for rule color.
- New option rulebetweencolor for environment parcolumns.

[2016/05/16 v1.4]

- Documentation updates.

[2019/12/29 v1.5]

- `\PassOptionsToPackage` not `\PassoptionsToPackage`

6 Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

| Symbols | |
|---|--|
| <code>\@M</code> | 51, 99 |
| <code>\@PackageWarningNoLine</code> | 84 |
| <code>\@empty</code> | 140 |
| <code>\@ifnextchar</code> | 144 |
| <code>\@one</code> | 25, 55, 103 |
| <code>\@nil</code> | 155, 160 |
| <code>\@tempa</code> | 47, 68, 80, 95, 117, 132 |
| <code>\@tempboxa</code> | 59, 63, 107, 112 |
| A | |
| <code>\advance</code> | 25, 55, 103 |
| C | |
| <code>\chardef</code> | 19, 29 |
| <code>\color</code> | 146, 151 |
| <code>\count@</code> .. | 23, 25, 26, 27, 29, 48, 54, 55, 56, 57, 60, 66, 70, 96, 102, 103, 104, 105, 108, 111, 115, 119 |
| <code>\csname</code> | 56, 57, 60, 66, 104, 105, 108, 115 |
| <code>\CurrentOption</code> | 6 |
| D | |
| <code>\DeclareOption</code> | 5 |
| <code>\define@key</code> | 138 |
| <code>\dp</code> | 61, 109 |
| E | |
| <code>\endcsname</code> | 56, 57, 60, 66, 104, 105, 108, 115 |
| <code>\endinput</code> | 16 |
| G | |
| <code>\g@addto@macro</code> | 39, 42 |
| H | |
| <code>\hb@xt@</code> | 49, 97 |
| <code>\hfill</code> | 72, 75, 121, 127 |
| <code>\hskip</code> | 57, 105 |
| I | |
| <code>\ifnum</code> | 21, 27, 54, 70, 102, 119 |
| <code>\ifpc@rulebetween</code> | 73, 122 |
| <code>\ifpdfcolAvailable</code> | 11 |
| <code>\ifvoid</code> | 56, 66, 104, 115 |
| <code>\ifx</code> | 82, 140 |
| L | |
| <code>\linewidth</code> | 49, 97 |
| <code>\loop</code> | 24, 53, 101 |
| M | |
| <code>\MessageBreak</code> | 85, 86, 87, 89 |
| N | |
| <code>\NeedsTeXFormat</code> | 2 |
| <code>\normalcolor</code> | 135 |
| <code>\number</code> | 34, 37, 56, 57, 60, 66, 104, 105, 108, 115 |
| P | |
| <code>\PackageInfo</code> | 13 |
| <code>\PassOptionsToPackage</code> | 6 |
| <code>\pc@alloccolumns</code> | 39 |
| <code>\pc@columncount</code> .. | 40, 54, 70, 102, 119 |
| <code>\pc@columnctr</code> | 43 |
| <code>\pc@placeboxes</code> | 68, 82, 85, 88, 94 |
| <code>\pc@setcolumnwidth</code> | 42 |
| <code>\pcpc@GobbleNil</code> | 148, 153, 160 |
| <code>\pcpc@InitStacks</code> | 20, 40 |
| <code>\pcpc@MaxStack</code> | 19, 21, 23, 29 |
| <code>\pcpc@RuleBetweenColor</code> | 124, 137, 141, 145, 150 |
| <code>\pcpc@RuleBetweenColorDefault</code> .. | 134, 137, 141 |
| <code>\pcpc@SetCurrent</code> | 36, 111 |
| <code>\pcpc@SwitchStack</code> | 33, 43 |
| <code>\pcpc@temp</code> | 139, 140, 143, 146, 151, 155, 157 |
| <code>\pdfcolInitStack</code> | 26 |
| <code>\pdfcolSetCurrent</code> | 37 |
| <code>\pdfcolSwitchStack</code> | 34 |
| <code>\ProcessOptions</code> | 8 |
| <code>\ProvidesPackage</code> | 3 |

| | | | |
|------------------------------------|-------------|------------------------------|------------|
| R | | U | |
| <code>\renewcommand</code> | 94 | <code>\unvbox</code> | 63, 112 |
| <code>\repeat</code> | 28, 78, 130 | V | |
| <code>\RequirePackage</code> | 9, 10, 18 | <code>\vbadness</code> | 51, 99 |
| S | | <code>\vbox</code> | 62, 110 |
| <code>\setbox</code> | 59, 107 | <code>\vfuzz</code> | 50, 98 |
| <code>\space</code> | 85, 87, 88 | <code>\vrule</code> | 74, 125 |
| <code>\splittopskip</code> | 52, 100 | <code>\vsplit</code> | 60, 108 |
| <code>\strut</code> | 71, 120 | X | |
| <code>\strutbox</code> | 61, 109 | <code>\x</code> | 46, 82 |
| T | | Z | |
| <code>\the</code> | 26 | <code>\z@</code> | 19, 48, 96 |
| | | <code>\z@skip</code> | 52, 100 |