Package 'websocket'

July 23, 2024

```
Version 1.4.2
Title 'WebSocket' Client Library
Description Provides a 'WebSocket' client interface for R.
      'WebSocket' is a protocol for low-overhead real-time communication:
     <https://en.wikipedia.org/wiki/WebSocket>.
License GPL-2
Encoding UTF-8
ByteCompile true
Imports R6, later (>= 1.2.0)
LinkingTo cpp11, AsioHeaders, later
BugReports https://github.com/rstudio/websocket/issues
SystemRequirements GNU make, OpenSSL >= 1.0.2
RoxygenNote 7.3.2
Suggests httpuv, testthat, knitr, rmarkdown
VignetteBuilder knitr
NeedsCompilation yes
Author Winston Chang [aut, cre],
     Joe Cheng [aut],
     Alan Dipert [aut],
     Barbara Borges [aut],
     Posit, PBC [cph],
     Peter Thorson [ctb, cph] (WebSocket++ library),
     René Nyffenegger [ctb, cph] (Base 64 library),
     Micael Hildenborg [ctb, cph] (SHA1 library),
     Aladdin Enterprises [cph] (MD5 library),
     Bjoern Hoehrmann [ctb, cph] (UTF8 Validation library)
Maintainer Winston Chang <winston@posit.co>
Repository CRAN
Date/Publication 2024-07-22 22:20:01 UTC
```

2 WebSocket

Contents

	ocket	Create a WebSocket client	
Index			5
	WebSocket		2

Description

```
WebSocket$new(url,
  protocols = character(0),
  headers = NULL,
  autoConnect = TRUE,
  accessLogChannels = c("none"),
  errorLogChannels = NULL,
  maxMessageSize = 32 * 1024 * 1024)
```

Arguments

url The WebSocket URL. Should begin with ws://orwss://.

protocols Zero or more WebSocket sub-protocol names to offer to the server during the

opening handshake.

headers A named list or character vector representing keys and values of headers in the

initial HTTP request.

autoConnect If set to 'FALSE', then constructing the WebSocket object will not automatically

cause the connection to be established. This can be used if control will return to R before event handlers can be set on the WebSocket object (i.e. you are constructing a WebSocket object manually at an interactive R console); after you are done attaching event handlers, you must call 'ws\$connect()' to establish

the WebSocket connection.

accessLogChannels

A character vector of access log channels that are enabled. Defaults to "none", which displays no normal, websocketpp logging activity. Setting accessLogChannels = NULL will use default websocketpp behavior. Multiple access logging levels may be passed in for them to be enabled.

A few commonly used access logging values are:

"all" Special aggregate value representing "all levels"

"none" Special aggregate value representing "no levels"

"rerror" Recoverable error. Recovery may mean cleanly closing the connection with an appropriate error code to the remote endpoint.

"fatal" Unrecoverable error. This error will trigger immediate unclean termination of the connection or endpoint.

All logging levels are explained in more detail at https://docs.websocketpp.org/reference_8logging.html.

WebSocket 3

errorLogChannels

A character vector of error log channels that are displayed. The default value is NULL, which will use default websocketpp behavior. Multiple error logging levels may be passed in for them to be enabled.

A few commonly used error logging values are:

"all" Special aggregate value representing "all levels"

"none" Special aggregate value representing "no levels"

"connect" One line for each new connection that is opened

"disconnect" One line for each new connection that is closed

All logging levels are explained in more detail at https://docs.websocketpp. org/reference_8logging.html.

maxMessageSize The maximum size of a message in bytes. If a message larger than this is sent, the connection will fail with the message_too_big protocol error.

Details

A WebSocket object has four events you can listen for, by calling the corresponding 'onXXX' method and passing it a callback function. All callback functions must take a single 'event' argument. The 'event' argument is a named list that always contains a 'target' element that is the WebSocket object that originated the event, plus any other relevant data as detailed below.

onMessage Called each time a message is received from the server. The event will have a 'data' element, which is the message content. If the message is text, the 'data' will be a one-element character vector; if the message is binary, it will be a raw vector.

onOpen Called when the connection is established.

onClose Called when a previously-opened connection is closed. The event will have 'code' (integer) and 'reason' (one-element character) elements that describe the remote's reason for closing.

onError Called when the connection fails to be established. The event will have an 'message' element, a character vector of length 1 describing the reason for the error.

Each 'onXXX' method can be called multiple times to register multiple callbacks. Each time an 'onXXX' is called, its (invisible) return value is a function that can be invoked to cancel that particular registration.

A WebSocket object also has the following methods:

connect() Initiates the connection to the server. (This does not need to be called unless you have passed 'autoConnect=FALSE' to the constructor.)

send(msg) Sends a message to the server.

close() Closes the connection.

readyState() Returns an integer representing the state of the connection.

©L: Connecting The WebSocket has not yet established a connection with the server.

1L: Open The WebSocket has connected and can send and receive messages.

2L: Closing The WebSocket is in the process of closing.

3L: Closed The WebSocket has closed, or failed to open.

4 WebSocket

setAccessLogChannels(channels) Enable the websocket Access channels after the websocket's creation. A value of NULL will not enable any new Access channels.

setErrorLogChannels(**channels**) Enable the websocket Error channels after the websocket's creation. A value of NULL will not enable any new Error channels.

clearAccessLogChannels(**channels**) Disable the websocket Access channels after the websocket's creation. A value of NULL will not clear any existing Access channels.

clearErrorLogChannels(channels) Disable the websocket Error channels after the websocket's creation. A value of NULL will not clear any existing Error channels.

Examples

```
## Only run this example in interactive R sessions
if (interactive()) {

# Create a websocket using the websocket.org test server
ws <- WebSocket$new("ws://echo.websocket.org/")
ws$onMessage(function(event) {
   cat("Client got msg:", event$data, "\n")
})
ws$onClose(function(event) {
   cat("Client disconnected\n")
})
ws$onOpen(function(event) {
   cat("Client connected\n")
})
# Try sending a message with ws$send("hello").
# Close the websocket with ws$close() after you're done with it.</pre>
```

Index

WebSocket, 2